


This document describes how to install the SupplyLogic Update program. The update program is used to update the SupplyLogic software on the Server, and Clients. The update program is also used to install the SupplyLogic Software on a client workstation.

Open a Browser and Review the Online Installation Instructions

- Open a browser and navigate to: <https://sl.cdrsupport.net>.
- From the menu, click Update.



Check the Current Version

- Review the **SupplyLogic Update Program** section for information on how to install it.
- If you have an existing **SL-Update** icon on the desktop, you may not need to update. Double click the desktop icon to open it. If the installed version matches what is displayed on the support site, you are up-to-date and don't need to do anything further.


SupplyLogic Update Program

The SupplyLogic Update program is used to download the latest SupplyLogic software.

SupplyLogic must already be installed on the computer before doing an update. The Server should always be done first then SupplyLogic should be opened on the server to verify the version number via Help, About. After the server version has been checked, each SupplyLogic client computer can then be done.


Follow these instructions to Install or Update the SL-Update program.

- Click on the link to start the download: [SL-Update Install \(2.23.01\)](#)




Updating SupplyLogic to the Latest version


- Click on the [SL-Update Install \(2.23\)](#) link to start the installation download.
- After it downloads, hover over the file and click "...". Select **Keep**. NOTE: make sure to hover over the file and select that "... " and not the "... " next to the push pin.




- Click the **Show More** link and select **Keep Anyway**



- Click on the **Open File** link to start the install



- At the "Windows Protected Your PC" screen select **More Info** and **Run Anyway**



- Run through the SL.Update installation (**Next, Next, Next, Yes, Close**)
- Find the **SL-Update** icon on the desktop and double-click to run it

SupplyLogic Support

Please contact the support team at Support@CDRSoftware.com for help. Also include the exact error you are getting and any relevant screenshots. Online Training can also be purchased at CDR's standard rate. It's a simple process, we send you a quote with a 5-hour minimum. Once you sign and return to us, someone will reach out to schedule training. You only pay for the hours you use and the contract expires at the end of the year.